# **boing Documentation**

Release 0.3.1

Paolo Olivo & Nicolas Roussel

Aug 28, 2017

# Contents

1	<b>Show</b> 1.1	vcase Boing documentation contents	<b>3</b> 3
Py	thon N	Module Index	45

Welcome! This is the documentation for Boing 0.3.1, last updated Aug 28, 2017.

Boing is a Python 3 toolkit designed to support the development of multi-touch and gesture enabled applications.

Boing enables to create pipelines for connecting different input sources to multiple target destinations (e.g. applications, logs, etc.) and eventually process the data before being dispatched. Boing provides a set of functional nodes that enable to:

- read and decode input sources (e.g. TUIO, OSC, JSON);
- encode and forward data to target outputs (e.g. TUIO, OSC, JSON);
- record and replay the data flow;
- process gesture data (calibration, smoothing filtering, debugging, etc.);
- debug and get statistics of the data flow.

Get started!

# CHAPTER 1

### Showcase

# **Boing documentation contents**

### Introduction

Boing enables to create pipelines for connecting different input sources to multiple target destinations (e.g. applications, logs, etc.) and eventually process the data before being dispatched.

As an example, consider the pipeline in *figure 1.1*: two tactile devices (left side) are connected to a single user application (top-right). At the same time, the contact events from both the devices are forwarded as a JSON stream to a second remote application (e.g. a contact visualiser), while an event recorder is used to log into a file the data stream provided by the second device only.



Fig. 1.1: Example of pipeline created using Boing.

Even if the tactile devices provides different data structures, Boing enables to merge them in a single data stream (in this example the TUIO and the JSON stream). Contact events are also processed before being passed to the

application: Boing provides nodes to smooth or calibrate the input data (e.g. position, speed, etc.). As shown in the example, pipelines can be composed by parallel branches so that each input/output can have its own processing suite.

Boing does not impose a specific data model; instead it exploits a query path language (similar to JSONPath) for accessing the data to be processed, so that it can fit a wide range of application domains.

### **Installing Boing**

#### Download

The current version is 0.3.1, released on September 18, 2012. Read the ChangeLog.

Download one of the following depending on your platform:

File	Туре	Py Version	Size
	Source	3.2	702KB
	Source	3.2	833KB
	MS Windows MSI installer	3.2	544KB

If you are interested to the development version, you can clone the source repository. Open a terminal and type:

```
git clone https://github.com/olivopaolo/boing
```

#### Installation

Boing requires the Python 3.2 interpreter (or newer) and the PyQt4 package (a set of Python bindings for Nokia's Qt application framework). Moreover, it also requires the following Python packages:

- numpy
- pyparsing

Extensive installation instructions are available for the following platforms:

#### Boing on Ubuntu 12.04

It is possible to install both Python and PyQt directly from the standard repositories by typing in a terminal:

```
sudo apt-get install python3-pyqt4 python3-setuptools python3-numpy
```

In order to complete the installation, open a terminal and type:

```
cd <BOING-DIRECTORY>
sudo python3.2 setup.py install
```

#### **Other Ubuntu releases**

• Ubuntu 11.04

#### Boing on OS X 10.7

#### **PyQt4 and Distribute**

If you have Mac Ports, getting PyQt4, numpy and Distribute is as simple as typing:

```
sudo port install py32-pyqt4 py32-distribute py32-numpy
```

#### Boing

In order to complete the installation, open a terminal and type:

```
cd <BOING-DIRECTORY>
sudo python3.2 setup.py install
```

The **boing** executable may be not installed into a directory indexed by the PATH variable, so that it is always necessary to use the full path to launch it. To avoid this annoying behaviour, a simple solution is to set the installer target directory using the option --install-scripts. As an example:

sudo python3.2 setup.py install --install-scripts /usr/local/bin

#### **Boing on Windows 7**

#### Python 3.2

First download the Python 3.2 binary installer and run it.

After Python has been installed, it may be useful to modify the PATH environment variable, so that Windows can find Python binaries and scripts without the need of specifing all the times the entire path. As an example, the PATH variable has been set to:

PATH = C:\Python32;C:\Python32\Scripts

#### PyQt4

Download the PyQt4 binary installer and run it.

#### **Distribute**

The package Distribute is necessary to run the boing's installer script. Download the file distribute\_setup.py and type in a terminal:

```
cd <DOWNLOAD-DIRECTORY>
python distribute_setup.py
```

#### numpy

Download the numpy binary installer and run it.

#### pyparsing

Download the source code of pyparsing, extract the archive and type in a terminal:

```
cd <PYPARSING-DIRECTORY>
python setup.py install
```

#### Boing

If you downloaded the binary installer you just have to launch it, otherwise extract the source archive and type in the terminal:

```
cd <BOING-DIRECTORY>
python setup.py install
```

#### Tests

After the installation has been completed, it may be useful to run the test suite in order to verify that everything has been correctly installed. In order to do so, type in a terminal:

python3 setup.py test

It is also possible to test only a subset of the Boing's modules:

```
cd <BOING-DIRECTORY>
python3 boing/test/run.py [MODULE [MODULE ...]]
```

The available modules are: core, filtering, gesture, net, nodes, utils. If no module is specified, all the available modules will be tested.

If you are interested to check the code coverage, you may use the tool called coverage by Ned Batchelder. Once the tool has been installed, you simply have to type:

```
cd <BOING-DIRECTORY>
coverage run --source boing boing/test/run.py
coverage report -m
```

### **Getting started**

This section contains various tutorials to easily learn to use the toolkit Boing:

#### **First steps**

This tutorial provides few simple examples of the functionality of the toolkit to help you starting to use the Boing toolkit.

Let's consider to have a multi-touch input device, like a tablet or a touch-screen. What cool things can I do with Boing? Boing enables to create a pipeline for connecting your device to different targets, like applications, frameworks, debuggers and eventually processing the gesture events before having being dispatched, like for example calibrate the contacts' position or apply a smoothing filter.

To make things easier, let's consider that your device can send the information of the contact events as a TUIO stream on the local port 3333.<sup>1</sup>

#### Showing multi-touch events

First of all, it is important to know that all the Boing's tools are invoked by using the script **boing**. Open a terminal and type:

boing "in.tuio://:3333 + viz:"

The script should have opened a window displaying a grid. Now when you touch your multi-touch device, you will be able to see the contact points appear on the window.

It's not difficult to notice that the script accepts a single argument that defines the configuration of the pipeline that is to be created. Configurations are defined by a formula where the operands define the functionality of the nodes of the pipeline, while the operators define how the nodes are connected, therefore also the structure of the pipeline.

In the previous example, the pipeline was composed by two nodes:

- in.tuio://:3333 corresponds to a node that reads the socket, decodes the TUIO stream and provides the multi-touch events;
- viz: corresponds to the *Contact Visualizer*, a widget that shows the information of the contact points, such as position, track and speed.

The two nodes are joined using the + operator, which stands for connection *in series*. The structure of the pipeline is represented in *figure 3.1*.



Fig. 1.2: Pipeline obtained from the configuration in.tuio://:3333 + viz:.

Congratulations! You have created your first Boing pipeline!

#### Exploring the data

Now, let's try new functionalities by adding a new node. Stop the previous pipeline by closing the visualizer widget or pressing Ctrl-C on the terminal, and type in the terminal:

boing "in.tuio://:3333 + (viz: | dump:)"

As before the contact visualizer appears again, but this time, when you touch the multi-touch device, the terminal prints a lot of data! The terminal output represents all the data that the in.tuio://:3333 node can produce and send to the connected nodes. This tutorial is not aimed to provide an exaustive description of the message structure; for the moment, simply observe that data messages are hierarchical structures mainly composed by Python built-in types, such as dictionaries, lists, strings, bytearrays, etc. Thanks to such standard structure, Boing exploits a query language, similar to JSONPath, for the indexing or the filtering of data messages. In order to understand the usefulness of such query language, stop the pipeline and type in the terminal:

<sup>&</sup>lt;sup>1</sup> If you are unfamiliar with the TUIO protocol, consider having a look to the available TUIO trackers, or jumping to the *Nodes reference table*, in order to discover the different ways Boing exploits to connect to the input devices.

```
boing "in.tuio://:3333 + (viz: | dump:?request=$..contacts)"
```

Now, when you touch your multi-touch device, you can see that the terminal prints the subset of the data structures that refers only to the contact data. This is because the query \$..contacts addresses to any data named as contacts, searched at any level of the structure. Such query language can be very useful during development and testing phases for highlighting only the relevant information.

A more exhaustive description of the data structure and of the query language can be found in the data model section. For now, let's leave the data structure and we consider the functioning of the pipeline: it's not difficult to understand that the | operator (*Pipe*) is used to connect in parallel the nodes viz: and dump:, so that the products are sent to both of them. *Figure 3.2* shows the structure of the current pipeline.



Fig. 1.3: Pipeline obtained from the configuration in.tuio://:3333 + (viz: | dump:).

#### Combining input sources with external applications

A key feature of Boing is the ability to provide the captured input events to external applications. This enables in most of the cases to take advantage of the toolkit's features without the need to adapt or to modify the applications, while sometimes a simple configuration may be required. As shown in *figure 3.3*, the Boing toolkit works as a semi-transparent layer placed between the input sources and the final applications.





Thanks to the many supported encodings, Boing can easily fit different combinations of devices and applications. In this basic example, let's consider to have an application listening for a TUIO stream on the local port 3335<sup>2</sup>. If you don't have a TUIO application, simply open a new terminal and launch a new Boing instance using the command:

boing "in.tuio://:3335 + viz:"

In the previous example you connected one input device to two output nodes. The | operator also enables to put in parallel different inputs, like for example a second multi-touch device enabled to send its TUIO messages to the local port 3334. Let's try a new pipeline by running the command:

boing "(in.tuio://:3333 | in.tuio://:3334) + (viz: | out.tuio://127.0.0.1:3335)"

Figure 3.4 shows the structure of the new pipeline.



Fig. 1.5: Pipeline obtained from the configuration (in.tuio://:3333 | in.tuio://:3334) + (viz: | out.tuio://127.0.0.1:3335).

As you can see, a very important feature of Boing is that you can simultaneously connect many devices to different applications. Such feature eases the usage of debugging tools and it enables multi-device and multi-user applications.

#### Data processing

The Boing toolkit is not only able to redirect input data to different destinations, but it also enables to process the transferred data. With regard to the multi-touch devices, recurring operations are the removal of the sensor noise and the calibration of the touch points. In order to accomplish these tasks, the toolkit provides two functional nodes that can be easily employed in our pipelines. As an example, let's run a new pipeline using the following command:

boing "in.tuio://:3333 + filtering: + calib:?screen=left + viz:"

Now, when you touch your tactile device you should still see the interactions on the visualizer widget, but now they look more smooth and they are rotated 90 degrees counterclockwise. By employing the filtering: node, we added the default smoothing filter, which is applied by default to the position of the contact points, while the node calib: performs the calibration of the touch points.

The structure of the current pipeline is shown in *figure 3.5*.

In order to better understand the result of the processing stage, it may be useful to show at the same time the raw data and the processed one. In order to achieve such result, stop the previous pipeline and run the following command:

<sup>&</sup>lt;sup>2</sup> For more output sources, see the *Nodes reference table*.



Fig. 1.6: Pipeline obtained from the configuration in.tuio://:3333 + filtering: + calib:?
screen=left + viz:

Now, when you touch your input device you can see on the visualizer widget both the raw tracks and the processed tracks, so that it is easier to note the effect of the processing stage. The structure of the modified pipeline is shown in *figure 3.6*. Note that this behaviour has been obtained by adding a parallel branch constituted only by the node nop:, which simply forwards the incoming data without making any modifications, and adding the node edit:? source=filtered, which labels the events of the processing branch so that they belong to the source *filtered* (the name is not relevant). This latter step is necessary since the data of the two parallel branches is merged into a single stream before being passed to the visualizer widget.



Fig. 1.7: Figure 3.6: Pipeline obtained from the configuration in.tuio://:3333 + (filtering: +
calib:?screen=left + edit:?source=filtered | nop:) + viz:

#### Event recording and replaying

The Boing toolkit also provides some tools for recording input events into log files and some other tools for replaying them. These operations are often really helpful during the development and debugging of applications. The simplest way to log events into a file is to use the node log:. As an example, consider running the following command:

boing "in.tuio://:3333 + (viz: | log:./log.bz2)"

Now, all the gestures you make on your tactile device will be recorded and written to the file . /log.bz2. Then, stop the pipeline by pressing Ctrl-C and let's replay the recorded gestures by executing the command:

boing "play:./log.bz2 + viz:"

Quite easy, isn't it? It is also possible to configure the player to endlessly rerun the log and set the replay speed. To do so, simply run this command:

boing "play:./log.bz2?loop&speed=0.2 + viz:"

A more powerful tool for replaying log files is the player: node: thanks to its GUI, it enables users to easily define a playlist of log files that the node will reproduce. As an example, run the following command:

boing "player: + viz:"

Playlists can be exported so that the player: tool becomes very useful during the application testing for executing the unit test.

#### Saving pipeline configurations

Sometimes it can be useful to store the configuration of the pipeline for later reuse. Writing long configurations in a terminal may also be quite annoying. For these reasons, Boing lets users to write the configuration of the pipeline in a text file and then to load such configuration using the special node conf:.

As an example, consider you have finally wrote the configuration of a pipeline for comparing the result of different smoothing filters. Now you want to save it in a file (e.g. config-filters.txt) and maybe you want to add some comments that will help you understanding the structure of the pipeline. The file may look like the following:

```
# Pipeline for comparing the result of different smoothing filters.
#
# Author: Me
# Date: Sept 12, 2012
# File: config-filters.txt
# ONE INPUT: a standard TUIO source
in.tuio://:3333
# PARALLEL BRANCHES
+ (
    # Raw input
    nop:
    # Default filter
    | filtering: + edit:?source=Default
    # Moving mean filter
    | filtering:/moving/average?winsize=5 + edit:?source=Mean
    # Moving median filter
    | filtering:/moving/median?winsize=5 + edit:?source=Median
    # Exponential double filter
    | filtering:/exponential/double?alpha=1&gamma=1 + edit:?source=Exponential
    # OneEuro filter
    filtering:/oneeuro?freq=1 + edit:?source=OneEuro
  )
# ONE OUTPUT: the visualizer
+ viz:
```

Now, in order to run the pipeline you just have to enter the command:

boing conf:./config-filters.txt

Quite easy, isn't it?

The node conf: is actually a composite node that contains the pipeline defined in the configuration file. For this reason, it is also possible to use the conf: node into another pipeline. Consider as an example that you have a multi-touch table sending contact information via the TUIO protocol, you found a good smoothing filter since the input is quite noisy and you also determined the calibration matrix to fit the touch position to the correct screen space. You are not going to change these parameters so you would like to consider all these elements as an atomic input source that does not mess up a larger configuration. Thus, first you could write the configuration of your input source into a file (e.g. my-mt-table.txt), which may look like the following:

```
# My multi-touch table without its ugly noise and well calibrated.
#
# Author: Me
# Date: Sept 12, 2012
# File: my-mt-table.txt
# INPUT: standard TUIO source
in.tuio://:3333
# FILTERING: OneEuro filter
+ filtering:/oneeuro?freq=60&merge
# CALIBRATION: my 4x4 matrix
+ calib:?merge&matrix=0.98,0,0,0.021,0,0.83,0,0.010,0,0,1,0,0,0,0,1
# NO OUTPUT, so I can reuse this into an external pipeline.
```

Then, you can reuse your configured input device as an atomic item in a new pipeline. As an example, let's show the contact events using the viz: node, and at the same time use the recorder widget and forward the contacts to an other application listening for a TUIO source on the local port 3334. The command to run is the following:

boing "conf:./my-mt-table.txt + (viz: | rec: | out.tuio://127.0.0.1:3334)"

As you can see, saving pipeline configurations into files can be quite useful in different situations. Needless to say that you can also use the conf: node inside a configuration written in a file, so that it is possible to arrange items in a hierarchical structure.

#### **Boing for developers**

Developers can easily deploy pipelines by invoking the *Boing's API* in their Python code. The function boing. create() can be used to instantiate the pipeline's nodes. This method requires as argument an URI expression that is used to specify the functionality of the nodes to be created and how they are connected. The *Nodes reference table* is the same as for the command line script. Then, the operators + and | can be used compose the pipeline.

The following code can be used as an example for creating Boing pipelines:

```
#!/usr/bin/env python3
import sys
import PyQt4
import boing
# Init application
app = PyQt4.QtGui.QApplication(sys.argv)
# Create nodes
n1 = boing.create("in.tuio://:3333")
n2 = boing.create("viz:")
n3 = boing.create("dump:?request=$..contacts")
# Compose the pipeline
graph = n1 + (n2 | n3)
# Run
sys.exit(app.exec_())
```

#### Todo

Describe an example of functional node.

### **Underlying concepts**

The documentation is structured into the following sections:

#### The pipeline architecture

Boing pipelines are made by directed graphs, where the edge direction defines the data flow between the nodes. There are three types of nodes:

- *producers* provide the data;
- consumers process the incoming data;
- workers are both consumers and producers;

The type of a node directly influences how the node can be connected to the other nodes: producers only accept outgoing connections, while consumers accept incoming connections only. Workers are composed by both the producer and consumer interfaces, so they can have both incoming and outgoing connections. *Figure 4.1* shows an example of both valid and invalid connections.



Fig. 1.8: Valid and invalid connections between producers (P), consumers (C) and workers (W).

#### The producer-consumer model

The core infrastructure of Boing pipelines is the producer-consumer model, which defines how the data is propagated through the pipeline. The model performs a pull technology, but it is extended by using the *Observer* pattern: consumers must subscribe to the producers in order to receive their products; for each subscribed consumer, producers keep a record containing the list of the pending products. When a producer has a new product, for each registered consumer it enqueues the product in the associated product list and it triggers the consumer, which synchronously or asynchronously can require its own pending products. Then, at the consumer's request, the producer sends all the correspondent pending products to the consumer and it cleans the correspondent buffer. The entire pipeline is run in a single thread, thus an eventloop is used to handle the asynchronous nodes. *Figure 4.2* shows the UML sequence diagram that defines the data exchange between producers and consumers.

#### See also:

classes boing.core.Producer and boing.core.Consumer

#### Supply and demand

In many situations, a data source can provide a wide range of information, but consumers may not be interested in all of it. For this reason, in order to save processing time, the model permits to assign a request to each consumer. Every time a producer has a new product, it tests the request of each registered consumer and only if it matches the product,



Fig. 1.9: UML sequence diagram defining the producer-consumer model

the producer notifies the consumer the new product. This behavior enables to process and transfer only the useful information, while the useless part is not processed. Requests can be added up so that a producer can easily know the entire request of all its registered consumers. The union of all the registered consumers' requests is called *aggregate demand*.

On the other side, it is good to know what a producer can supply. For this reason the model permits to assign an offer to the producers, which must be the list of templates of the products it can provide. Using its offer, a producer can say a priori whether it can meet a consumer's request. Composing the offer and the aggregate demand, it is possible to calculate the *demanded offer*, which represents the subset of the offer that is currently being demanded.

As an example, consider two producers P1 and P2 and two consumers C1 and C2 connected as shown in *figure 4.3*. It is possible to observe that the aggregate demand of P1 is equal to the union of the requests of both C1 and C2. Moreover, even if P1 produces both A and B, only the products A are sent to C1, while both A and B products are sent to C2. Also note that P2's *demandedOffer* is only B, because P2 is only connected to C2 and this one does not require the products C.

**Note:** It is important to understand that a node's offer does not impose that the only products that the nodes produces are coherent with the offer and even that it is sure that the node will ever produce such products. The offer is only used to describe the node standard behavior. *It's easier said than done!* 

#### See also:

classes boing.core.Offer and boing.core.Request

As previously seen, it is possible to create long pipelines by serializing worker nodes. In order to spread the supply and demand strategy, a worker node must be able to propagate the requests of the consumers it is connected to in addition to its own request and to propagate the offer of the producers it is connected to in addition to its own offer. In order to understand such necessity, consider the pipeline shown in *figure 4.4*: in this case the worker *W* is not propagating its



Fig. 1.10: Example of supply and request behavior.

neighbors' requests and offers (the variables *isPropagantingRequest* and *isPropagatingOffer* are false), so that its own request and offer, which are defined by the variables *\_selfRequest* and *\_selfOffer*, are actually the same of its (public) request and offer. In this case, it is possible to notice that even if the consumer C require the products B, such demand is hidden by the worker W, so that even if the producer P can provide B products, it can't see anyone interested to them, so they are not produced.



Fig. 1.11: The worker W is not propagating its connected consumers' requests, thus the producer P does not provides the products B.

The *figure 4.5* shows the same pipeline as before with the difference that the worker W is now propagating its neighbors' requests and offers. It is possible to notice that the request of W is equal to the union of the request of C and its own request, and its public offer is equal to the union of the offer of P and its own offer. W is now requiring B products because a subsequent node is also requiring them, thus P will produce and dispatch them.



Fig. 1.12: Example of supply and request behavior.

**Note:** It is important to understand that the variables *isPropagatingRequest* and *isPropagatingOffer* do not control the output of *W*, but only the fact that its request and offer are determined by accumulating the neighbors requests and offers. The fact that *W* forwards *B* products only depends on the specific implementation of *W*. See class boing. core.Functor for product forwarding cases.

#### The wise worker and the auto-configuration feature

As formerly described, *worker* nodes are both consumers and producers, and they can be considered as the pipeline's processing units. Workers normally calculate simple or atomic operations because they can be easily serialized in order to compose more complex processing pipelines. Boing pipelines can be modified dynamically in order to evolve and fit a flexible environment. This may entail that not all the processing units are really necessary in order to compute the expected result. In order to avoid a waste of time, the pipeline exploits a auto-configuration technique based on the nodes' supply-demand knowledge. This technique, exploited by the *Wise Workers*, can be summarized into the following two rules:

- 1. the worker's request is nullified if no one requires the worker's own products;
- 2. the worker's offer is nullified if its own request is not satisfied.

As an example consider the pipeline in *figure 4.6*: the producer P provides the products A, which are required by the consumer C; this one also requires the products B, but P cannot provide them. For this reason the worker W, which can produce B from A, has been employed. Since B is required by C, W is currently active. In this example the worker W is set to forward all the products it receives even it is not directly interested to them.



Fig. 1.13: The producer P provides the products A, while the worker W produces the products B using the products A. Both A and B are actually required by the consumer C.

Now suppose that the consumer C changes its own request to A only. In this case, nobody is interested to B anymore, thus, following the first rule of the *Wise Worker*, the worker stops requiring A for itself and it passes into an inactive state, but, since it is propagating C's requests, it still requires A products. *Figure 4.7* shows the state of the pipeline in this case.



Fig. 1.14: If C does not require products B anymore, the worker W automatically stops producing them and requiring A products for itself, but since it is propagating C's requests, it still requires A products so it can forward them to C.

Considering the pipeline in *figure 4.6*, a different situation may arrive: if the producer P changes its offer to D, no one will provide the products A, thus, following the second rule of the *Wise Worker*, since the worker's request is not satisfied anymore, it nullifies its own offer. The resulted pipeline is shown in *figure 4.8*. In this case requests do not change, so that no more products are exchanged between the nodes.

In some cases workers do not previously know the products they provide since it only depends on the products they will receive. As an example, a worker may forward only a subset of the products it receives or it may make simple changes to the products it requires and then forward them. In those cases, it is not possible to set the offer in advance



Fig. 1.15: Considering the pipeline of *figure 4.6*, if the producer *P* starts producing *D* only, the worker's request is not satisfied anymore, so it automatically nullifies its own offer.

of the pipeline execution, thus the first rule of the *Wise Worker* cannot be applied. In order to handle those cases, the *Wise Workers* can use the *Tunneling* exception, that makes the first rule considering the entire propagated offer instead of the worker's own offer.

As an example consider the pipeline in *figure 4.9*: the worker W simply forwards the products it receives so it has not its own offer. Despite this, thanks to the tunneling exception, W is still active, since its global offer matches the request of C.



Fig. 1.16: When using the tunneling option, the propagated offer is considered to determine if the worker is active instead of its own offer only.

Concrete workers using the tunneling feature are the Filter and Calibration classes.

#### See also:

```
classes boing.core.economy.WiseWorker and boing.core.Functor
```

### Todo

• Describe the composite nodes and node syntax (+ and | operators).

### **Nodes reference table**

Node URIs				
OSs Mode Value Query keys <sup>1</sup>			Description Data Redirection	
LWX I			listen and decode data from an input device	
LWX O			encode and forward the data to a target	
			destination Record/Replay	
LWX I		loop, speed, interval	replay a log file (default encoding)	
LWX O			record data to log file (default encoding)	
LWX O	rec:	request, timelimit, sizelimit,	data recorder with GUI	
		oversizecut, fps, timewarping		
LWX I		interval, open	log files player with GUI (default encoding)	
			Data Debug	
LWX O		request, mode, separator, src,	dump products to an output device	
		dest, depth		
LWX O		request, fps	print products statistics to an output device	
LWX O	viz:	antialiasing, fps	display multi-touch contacts Data Processing	
LWX W	nop:		no operation node	
LWX W	edit:	merge, copy, result, **dict	apply to all the received products **dict	
LWX W	calib:	matrix, screen, attr, request,	apply a 4x4 transformation matrix	
		merge, copy, result		
LWX W	filtering:[ <filte< td=""><td>r-attr, request, merge, copy, result,</td><td>filter product data</td></filte<>	r-attr, request, merge, copy, result,	filter product data	
	path>]	<filter-attr><sup>2</sup></filter-attr>		
LWX W	timekeeper:	merge, copy, result	mark each received product with a timetag	
LWX W	lag:[ <msec>]</msec>		add a lag to each received product Utils	
LWX <sup>3</sup>	conf: <filepath></filepath>	>	composite node containing the pipeline defined	
			into the specified configuration file.	

### Encodings

Encodings <sup>4</sup>				
OSs	Mode	Value	Query keys	Description
LWX	IO	slip		bytestream from/to SLIP
LWX	Ι	pickle	noslip	pickle to products
LWX	0	pickle	protocol, request, noslip	Products to pickle
LWX	Ι	json	noslip	JSON to products
LWX	0	json	request, noslip	products to JSON
LWX	IO	OSC	rt, noslip	bytestream from/to OSC
LWX	IO	tuio[.osc]	rawsource	Multi-touch events from/to TUIO

<sup>&</sup>lt;sup>1</sup> The available query keys are obtained from the union of the available query keys of all the uri components. As an example, the URI out.json://[::1]:7777 is by default translated to out.json.udp://[::1]:7777, so it owns the query keys of the JSON encoder (request and filter) and of the udp socket node (writeend). <sup>2</sup> <filter-attr> dependes on the requested filter.

<sup>&</sup>lt;sup>3</sup> The *mode* depends on the pipeline defined into the configuration file. It is important to note that pipelines may have a closed configuration, which means they do not behave neither as input nor output, nor worker. This happens when all the inputs are connected in series to the outputs.

<sup>&</sup>lt;sup>4</sup> Some encodings have default input/output devices (e.g. in.tuio: is by default translated into in.tuio.udp://[::]:3333).

### Input/Output devices

Input/Output devices				
OSs	Mode	Value	Query keys	Description
LX	Ι	:[stdin]		read from standard input
LWX	Ι	:[stdout]		write to standard output
LWX	Ι	[.file]: <filepath></filepath>	uncompress, postend	read from file
LWX	0	[.file]: <filepath></filepath>		write to file
LWX	Ι			read from UDP socket
LWX	0		writeend	write to UDP socket
LWX	IO		writeend	read/write on TCP socket

#### Hosts

Hosts				
OSs	Mode	Value	Description	
LWX	Ι	empty	same as IPv4 any address	
LWX	Ι	0.0.0.0	IPv4 any address	
LWX	Ι	[::]	IPv6 any address	
LWX	IO	127.0.0.1	IPv4 loopback	
LWX	IO	[::1]	IPv6 loopback	
LWX	IO	X.X.X.X	specific IPv4 address	
LWX	IO	[x:x:x:x:x:x:x]	specific IPv6 address	
LWX	IO	<hostname></hostname>	specific hostname	

#### Modes

Modes		
Value	Description	
Ι	Input	
0	Output	
W	Worker	

#### See also:

Section *The pipeline architecture* 

### **OS support**

OS support		
Value	Description	
L	Linux	
W	Windows 7 <sup>5</sup>	
Х	OS X	

<sup>5</sup> On Windows, in order to define a file using the scheme file: it is necessary to place the character '/' (slash) before the drive letter (e.g. file:///C:/Windows/explorer.exe).

### **API documentation**

This section presents the different modules that constitute the toolkit Boing. The documentation of the classes and functions of the toolkit's API is hereinafter provided.

The Boing toolkit is structured into the following modules:

#### boing — Creating and managing pipelines

Developers can easily deploy Boing pipelines by invoking the toolkit's API in their Python code. The most important element is the function *boing.create()*, which is used to instantiate the nodes of the pipeline.

boing.create(expr, parent=None)

Return a new node created as defined in the expression *expr*, with parent object *parent*. If *expr* is composed by a single URI, the returned object will be a new node correspondent to the provided URI; if *expr* is formed by an URI expression, the returned object will be a composed node.

All the available nodes are listed and described in the Nodes reference table.

In order to compose the pipeline, the nodes can be attached using the Python operators + and |, which work the same as the operators used in the URI expressions. As an example, consider the following code:

```
n1 = boing.create("in.tuio:")
n2 = boing.create("viz:")
n3 = boing.create("dump:")
pipeline = n1 + (n2 | n3)
```

The same pipeline can be obtained using the following code:

pipeline = boing.create("in.tuio:+(viz:|dump:)")

In order to run the pipeline it is necessary to launch the Qt Application that should have been initialized before creating the pipeline. The following code can be used as an example for creating custom Boing pipelines:

```
#!/usr/bin/env python3
import sys
import PyQt4
import boing
# Init application
app = PyQt4.QtGui.QApplication(sys.argv)
# Create nodes
n1 = boing.create("in.tuio:")
n2 = boing.create("viz:")
n3 = boing.create("dump:?request=$..contacts")
# Compose the pipeline
graph = n1 + (n2 | n3)
# Run
sys.exit(app.exec_())
```

#### **Global configuration**

The attribute *boing.config* is a dict object used to store any global configuration variable.

boing.config

dict object used to store any global configuration variable. Boing's own variables:

•"--no-gui": set to True when GUI is disabled.

#### **Dynamic configuration**

#### Todo

Describe how to configure the pipeline dinamically

boing.activateConsole (*url=""*, *locals=None*, *banner=None*) Enable a Python interpreter at *url*.

The optional *locals* argument specifies the dictionary in which code will be executed; it defaults to a newly created dictionary with key "\_\_name\_\_" set to "\_\_console\_\_" and key "\_\_doc\_\_" set to None.

The optional *banner* argument specifies the banner to print before the first interaction; by default it prints a banner similar to the one printed by the real Python interpreter.

#### boing.core — The pipeline infrastructure

The module *boing.core* contains the classes that constitute the infrastructure of Boing pipelines.

```
class boing.core.Offer(*args, iter=None)
```

An offer defines the list of products that a producer advertises to be its deliverable objects.

Offer.UNDEFINED can be used to define the producer's offer, when the real offer cannot be defined a priori. This avoids to have empty offers, when they cannot be predeterminated.

#### class boing.core.Request

The class Request is an abstract class used by Consumer objects for specifing the set of products they are insterested to. The method test () is used to check whether a product matches the request.

Request.NONE and Request.ANY define respectively a "no product" and "any product" requests.

Request objects may also indicate the internal parts of a product to which a producer may be interested. The method *items()* returns the sequence of the product's parts a producer is interested to.

The class Request implements the design pattern "Composite": different requests can be combined into a single request by using the sum operation (e.g. comp = r1 + r2). A composite request matches the union of the products that are matched by the requests whom it is composed. Request . NONE is the identity element of the sum operation.

Request objects are immutable.

```
test (product)
```

Return whether the *product* matches the request.

```
items (product)
```

Return an iterator over the *product*'s internal parts (i.e. (key, value) pairs) that match the request.

```
class boing.core.QRequest (string)
```

The QRequest is a Request defined by a QPath.

class boing.core.Producer(offer, tags=None, store=None, retrieve=None, haspending=None, parent=None)

A Producer is an observable object enabled to post products to a set of subscribed consumers.

When a producer is demanded to posts a product, for each registered consumer it tests the product with the consumer's request and only if the match is valid it triggers the consumer.

Each Producer has an Offer (a list of product templates), so it can say if a priori it can meet a consumer's request.

#### demandChanged

Signal emitted when the aggregate demand changes.

#### offerChanged

Signal emitted when its own offer changes.

#### ${\tt demandedOfferChanged}$

Signal emitted when its own demanded offer changes.

#### aggregateDemand()

Return the union of all the subscribed consumers' requests.

#### demandedOffer()

Return the producer's demanded offer.

#### meetsRequest()

Return whether the product's offer meets request.

#### offer()

Return the producer's offer.

#### postProduct (product)

Post *product*. In concrete terms, it triggers the registered consumers that require *product*, then it stores the product.

#### class boing.core.Consumer(request, consume=None, hz=None, parent=None)

A Consumer is an observer object that can be subscribed to many producers for receiving their products. When a producer posts a product, it triggers the registered consumers; the triggered consumers will immediately or at regular time interval demand the producer the new products.

Many consumers can be subscribed to a single producer. Each new product is actually shared within the different consumers, therefore a consumer SHOULD NOT modify any received product, unless it is supposed to be the only consumer.

Consumers have a request. When a producer is demanded to posts a product, it tests the product with the consumer's request and only if the match is valid it triggers the consumer.

A consumer's request must be an instance of the class Request. The requests "any product" and "no product" are available.

#### request()

Return the consumer's request.

\_consume (*products*, *producer*) Consume the *products* posted from *producer*.

#### boing.filtering - Filters and noise generators

Smoothing filters and noise generators.

#### Todo

Comment module boing.filtering.

#### boing.gesture — Gesture recognition tools

Recognition algorithms and common utilities have been placed in separated submodules:

#### boing.gesture.rubine — The Rubine's recognition algorithm

The module *boing.gesture.rubine* provides an implementation of the Rubine's gesture recognition algorithm.

#### boing.gesture.utils — Recognizers' common utilities

The boing.gesture.utils module contains common method used by different recognizers.

boing.gesture.utils.boundingBox(points)

Return the tuple (minx, miny, maxx, maxy) defining the bounding box for points.

#### boing.gesture.utils.updateBoundingBox(bb1, bb2)

Return the tuple (minx, miny, maxx, maxy) defining the bounding box containing the bounding boxes *bb1* and *bb2*.

#### boing.net — Networking and encoding tools

The module *boing.net* provides classes and methods to ease the usage of sockets and networking encodings, like for example JSON, OSC, SLIP, etc.

#### class boing.net.Encoder

The Encoder class is the abstract base class for implementing the encoders of all the different encodings.

class boing.net.Decoder

The Decoder class is the abstract base class for implementing the decoders of all the different encodings.

The Decoder class implements the composite pattern. Many decoders can be put in sequence into a single composed decoder using the sum operator.

Each encoding has been implemented in a different submodule:

#### boing.net.bytes — UNICODE encoding

The *boing.net.bytes* module implements the adapter design pattern by providing the standard string encoding functionalities as Encoder and Decoder objects.

boing.net.bytes.encode (string, encoding="utf-8", errors="strict")

Return an encoded version of *string* as a bytes object. Default encoding is 'utf-8'. *errors* may be given to set a different error handling scheme. The default for errors is 'strict', meaning that encoding errors raise a UnicodeError. Other possible values are 'ignore', 'replace', 'xmlcharrefreplace', 'backslashreplace'

boing.net.bytes.decode(data, encoding="utf-8", errors="strict")

Return a string decoded from the given bytes. Default *encoding* is 'utf-8'. *errors* may be given to set a different error handling scheme. The default for errors is 'strict', meaning that encoding errors raise a UnicodeError. Other possible values are 'ignore', 'replace' and any other name registered via codecs.register\_error().

#### class boing.net.bytes.Encoder (encoding="utf-8", errors="strict")

The Encoder is able to produce encoded version of string objects as byte objects.

#### encode (string)

Return an encoded version of string as a bytes object.

**reset**() NOP method.

```
class boing.net.bytes.Decoder (encoding="utf-8", errors="strict")
The Decoder is able to convert byte objects into strings.
```

decode (data)

Return the list of strings decoded from the given bytes.

reset()

NOP method.

#### boing.net.slip — SLIP encoding

The module *boing.net.slip* provides methods and classes for supporting the SLIP protocol encoding and decoding.

```
boing.net.slip.encode(data)
```

Return a slip encoded version of data.

boing.net.slip.decode(data, previous=None)

Return the list of bytearrays obtained from the slip decoding of *data* followed by the undecoded bytes. If previous is not None, *data* is appended to previous before decoding. A typical usage would be:

```
buffer = bytearray()
decoded, buffer = decode(data, buffer)
```

#### class boing.net.slip.Encoder

The Encoder is able to produce slip encoded version of byte strings.

#### encode (*obj*)

Return a slip encoded version of the byte string obj.

#### reset()

NOP method.

#### class boing.net.slip.Decoder

The Decoder object is able to decode slip encoded byte strings into the their internal components.

#### decode(obj)

Return the list of bytearrays obtained from the slip decoding of *obj*.

```
reset()
```

Reset the slip internal buffer.

#### boing.net.json — JSON encoding

The module *boing.net.json* provides methods and classes for supporting JSON object serialization. It uses the python json standard module, but it provides a default solution for serializing bytestrings and datetime.datetime objects.

Encoder and Decoder classes provide a standard interface for the JSON encoding.

```
boing.net.json.encode (obj)
Return a string containing the json serialization of obj.
```

#### boing.net.json.decode(string)

Return the object obtained for decoding string using the JSON decoding.

**class** boing.net.json.**Encoder** The Encoder is able to serialize standard data types into json strings.

encode(obj)

Return a string containing the json serialization of obj.

reset()

NOP method.

class boing.net.json.Decoder

The Decoder object is able to decode json strings into the corrispetive python objects.

decode (string)

Return the list of object obtained from the deserialization of string.

reset () NOP method.

#### boing.net.osc — OSC encoding

The module *boing.net.osc* provides methods and classes for handling OSC formatted messages.

Encoder and Decoder classes provide a standard interface for the OSC encoding.

#### class boing.net.osc.Encoder

The Encoder is able to encode OSC packet objects into byte strings.

```
encode (obj)
```

Return the bytestring obtained from serializing the OSC packet obj.

```
reset()
```

NOP method.

#### class boing.net.osc.Decoder

The Decoder is able to convert valid byte string objects into OSC Packet objects.

#### decode (obj)

Return the list of OSC packets decoded from the bytestring obj.

reset()

Reset the slip internal buffer.

#### boing.net.pickle — Python pickle encoding

The module *boing.net.pickle* provides methods and classes for supporting Python object serialization. It uses the python pickle standard module.

Encoder and Decoder classes provide a standard interface for the pickle encoding.

#### boing.net.pickle.encode(obj, protocol=None)

Return the pickled representation of *obj* as a bytes object.

The optional protocol argument tells the pickler to use the given protocol; supported protocols are 0, 1, 2, 3. The default protocol is 3; a backward-incompatible protocol designed for Python 3.0.

Specifying a negative protocol version selects the highest protocol version supported. The higher the protocol used, the more recent the version of Python needed to read the pickle produced.

#### boing.net.pickle.decode(data)

Read a pickled object hierarchy from the bytes object *data* and return the reconstituted object hierarchy specified therein.

The protocol version of the pickle is detected automatically, so no protocol argument is needed. Bytes past the pickled object's representation are ignored.

#### class boing.net.pickle.Encoder

The Encoder is able to serialize Python objects into pickle bytestrings.

#### encode (obj)

Return the pickled representation of *obj* as a bytes object.

The optional protocol argument tells the pickler to use the given protocol; supported protocols are 0, 1, 2, 3. The default protocol is 3; a backward-incompatible protocol designed for Python 3.0.

Specifying a negative protocol version selects the highest protocol version supported. The higher the protocol used, the more recent the version of Python needed to read the pickle produced.

#### reset()

NOP method.

#### class boing.net.pickle.Decoder

The Decoder object is able to decode pickle bytestrings into the corrispetive objects hierarchy.

#### decode (obj)

Read a pickled object hierarchy from the bytes object *data* and return the reconstituted object hierarchy specified therein.

The protocol version of the pickle is detected automatically, so no protocol argument is needed. Bytes past the pickled object's representation are ignored.

#### reset()

Reset the slip internal buffer.

Common networking utilities:

#### boing.net.ip — IP utilities

The module *boing.net.ip* provides few functions related to IP addressing.

boing.net.ip.resolve(addr, port, family=0, type=0)

Return a pair (addr, port) representing the IP address associated to the host *host* for the specified port, family and socket type.

boing.net.ip.addrToString(addr)
 Return a string representing the QHostAddress addr.

#### boing.net.tcp — TCP utilities

#### Todo

Improve docs for the module boing.net.tcp

#### boing.net.udp — UDP utilities

#### Todo

Improve docs for the module boing.net.udp

#### boing.net.ntp — NTP utilities

The module *boing.net.ntp* provides few functions for handling the Network Time Protocol (NTP).

Example:

```
import datetime
from boing.net import ntp
srvtime = ntp.ntpFromServer("europe.pool.ntp.org")
srvdatetime = ntp.ntp2datetime(srvtime)
now = datetime.datetime.now()
print("Server time:", srvdatetime)
print("Local time:", now)
print("Delta:", now - srvdatetime)
```

boing.net.ntp.ntpEncode(t)

Return the bytes object obtained from encoding the POSIX timestamp t.

```
boing.net.ntp.ntpDecode (data)
Return the POSIX timestamp obtained from decoding the bytes object data.
```

#### boing.net.ntp.ntpFromServer(server)

Send an ntp time query to the *server* and return the obtained POSIX timestamp. The request is sent by using an UDP connection to the port 123 of the NTP server.

#### boing.net.ntp.ntp2datetime(t)

Return the datetime.datetime instance corresponding to the POSIX timestamp t.

#### boing.net.ntp.datetime2ntp(dt)

Return the POSIX timestamp corresponding to the datetime.datetime instance dt.

#### boing.nodes — The nodes of the pipeline

The module *boing.nodes* contains a set of generic utility nodes.

#### **Products debugging**

class boing.nodes.Dump (request=Request.ANY, mode='items', separator='\n\n', src=False, dest=False,

*depth=None*, *parent=None*)

Instances of the *Dump* class produce a string representation of the products they receive. The string is obtained using the function *boing.utils.deepDump()*.

The parameter *request* must be an instance of the class boing.core.Request and it is used to select the product to be dumped. The default value for request is Request.ALL. *mode* defines how the received products will be dumped. The available values are:

• 'keys', only the matched keys are written;

- 'values', only the values of the matched keys are written;
- •'items', both the keys and values are written.

*separator* defines the string to be written between two products. The default value for separator is  $\nn'$ . *src* defines whether the node also dumps the producer of the received products. The default for src is False. The parameter *dest* defines whether the node adds a reference to itself when it dumps the received products; its default value is False. The parameter *depth* defines how many levels of the data hierarchy are explored and it is directly passed to the *boing.utils.deepDump()* function.

#### mode ()

Return the node's mode.

#### setMode (mode)

Set the node's dump mode.

#### **Products editing**

class boing.nodes.Editor(dict, blender, parent=None)

Instances of the *Editor* class apply to the received products the (key, values) pairs of *dict*.

*blender* defines the output of the node (see boing.core.Functor). *parent* must be a PyQt4.QtCore. QObject and it defines the node's parent.

```
get (key, default=None)
```

Return the value for *key* if *key* is in the editor's dictionary, else *default*. If *default* is not given, it defaults to None.

set (key, value)

Set the value for *key* to *value*.

items()

Return a new view of the editor dictionary's items ((key, value) pairs).

#### class boing.nodes.DiffArgumentFunctor (functorfactory, request, blender=Functor.MERGECOPY,

### parent=None)

It takes a functorfactory and for each different argument path, it creates a new functor which is applied to the argument value. The args must be a diff-based path so that functor can be removed depending on 'diff.removed' instances.

#### **Timing utilities**

#### class boing.nodes.Timekeeper(blender=Functor.MERGECOPY, parent=None)

Instances of the *Timekeeper* class tag each received product with the timestamp when the product is received; then they forward the product.

*blender* defines the output of the node (see boing.core.Functor). *parent* must be a PyQt4.QtCore. QObject and it defines the node's parent.

```
class boing.nodes.Lag(msec, parent=None)
```

Instances of the Lag class forward the received products after a delay.

The parameter *msec* defines the lag in milliseconds. *parent* must be a PyQt4.QtCore.QObject and it defines the node's parent.

#### boing.utils — Common utilities

The module *boing.utils* contains generic utility classes and functions.

boing.utils.assertIsInstance(obj, \*valid)

Raise TypeError if *obj* is not an instance of a class in *valid*.

- boing.utils.deepDump (*obj*, *fd=sys.stdout*, *maxdepth=None*, *indent=2*, *end="n"*, *sort=True*) Write to *fd* a textual representation of *obj*.
- **class** boing.utils.**Console** (*inputdevice*, *outputdevice*, *banner="""*, *locals=None*, *parent=None*) Interactive Python console running along the Qt eventloop.

push(line)

Pass line to the Python interpreter.

#### Submodules

boing.utils.url — Uniform Resource Locator

The module *boing.utils.url* mainly provides the class *URL*, which is used to represent a Uniform Resource Locator.

class boing.utils.url.URL (string)

An instance of the class *URL* represents an Uniform Resource Locator (URL). The attribute *string* of the class constuctor defines the URL that the instance will represent; at the instance initialization, *string* is parsed in order to detect the kind of URL and to separate it into the specific components: *schema*, *site*, *path*, *query*, *fragment*.

Usage example:

```
>>> from boing.utils.url import URL
>>> url = URL("ftp://paolo:pwd@localhost:8888/temp?key=value#frag")
>>> url.scheme
'ftp'
>>> url.site.user
'paolo'
>>> url.site.password
'pwd'
>>> url.site.host
'localhost'
>>> url.site.port
8888
>>> str(url.path)
'/temp'
>>> url.query['key']
'value'
>>> url.fragment
'frag'
```

Each instance owns the following read-only attributes:

#### kind

Kind of URL. It equals to one of the following:

•URL.EMPTY — empty URL
•URL.OPAQUE — URL like <scheme>: <opaque>
•URL.GENERIC — URL like <scheme>: //<site>/<path>?<query>#<fragment>

•URL.NETPATH --- URL like //<site>/<path>?<query>#<fragment>

```
•URL.ABSPATH --- URL like /<path>?<query>#<fragment>
```

•URL.RELPATH - URL like <path>?<query>#<fragment>

#### scheme

URL scheme defined by a str.

#### **site** URL site defined by an instance of the class URL\_site.

#### path

URL path defined by an instance of the class URL\_path.

query

URL query defined by an instance of the class URL\_query.

#### fragment

URL fragment defined by a str.

#### opaque

if the URL is of kind URL.OPAQUE it defines the right part of the URL; otherwise it is set by default to the empty string "".

The string representation of an *URL* instance is normally equal to the string passed at the instance initialization, but there are few exceptions:

```
>>> str(URL("udp://:3333"))
'udp://:3333'
>>> str(URL("udp://:3333:0"))
'udp://:3333'
>>> str(URL("file:/tmp/log"))
'file:///tmp/log'
```

URL instances are equal if their string representation is the same:

```
>>> URL("udp://:3333") ==URL("udp://:3333")
True
>>> URL("udp://:3333:0") ==URL("udp://:3333")
True
```

URL instances can be compared to str objects:

```
>>> URL("udp://:3333")=="udp://:3333"
True
```

and they can be concatenated as they were str objects:

```
>>> url = URL("udp://:3333")
>>> "osc."+url
'osc.udp://:3333'
>>> url+"#frag"
'udp://:3333#frag'
```

Note that the result is a str, not an URL instance.

#### **URL internal classes**

```
class boing.utils.url.URL_site (string)
```

Used to store the component site of an URL. Each instance owns the following attributes:

#### user

User defined by a string.

#### password

Password defined by a string. It is NOT encripted.

#### host

Site host defined by a string.

#### port

Port number defined by an integer. It defaults to 0.

Usage example:

```
>>> url = URL("ftp://paolo:pwd@localhost:8888")
>>> url.site
URL_site('paolo:pwd@localhost:8888')
>>> print(url.site)
paolo:pwd@localhost:8888
>>> url.site.user
'paolo'
>>> url.site.password
'pwd'
>>> url.site.host
'localhost'
>>> url.site.port
8888
```

Instances can be compared to str objects:

```
>>> url = URL("udp://localhost:3333")
>>> url.site=="localhost:3333"
True
```

and have Boolean value to True if anyone of the component attributes is defined:

```
>>> bool(URL("udp://localhost:3333").site)
True
>>> bool(URL("udp://").site)
False
```

#### Warning: Pay attention to the default case:

```
>>> bool(URL("udp://:0").site)
False
```

```
class boing.utils.url.URL_path(string)
```

Used to store the component *path* of an URL. Usage example:

```
>>> url = URL("file:///tmp/log")
>>> url.path
URL_path('/tmp/log')
```

```
>>> print(url.path)
/tmp/log
>>> url.path.isAbsolute()
True
```

#### isAbsolute()

Return wheter the path is absolute:

```
>>> URL("file:///tmp/log").path.isAbsolute()
True
>>> URL("/tmp/log").path.isAbsolute()
True
>>> URL("file").path.isAbsolute()
False
>>> URL("./file").path.isAbsolute()
False
```

Instances can be compared to str objects:

```
>>> url = URL("file:///tmp/log")
>>> url.path=="/tmp/log"
True
```

and have Boolean value to True if the URL path is not empty:

```
>>> bool(URL("file:///tmp/log").path)
True
>>> bool(URL("/").path)
True
>>> bool(URL("udp://:8888").path)
False
```

Warning: Pay attention to the default transformation:

```
>>> str(URL("file:/tmp/log"))
'file:///tmp/log'
```

#### class boing.utils.url.URL\_query(string)

Used to store the component *query* of an URL. This class implements the collections.MutableMapping *ABC*. It is also able to encode the URL's *query* into a "percent-encoded" string.

Usage examples:

### **Getting help**

The easiest way to get help with the project is to join the mailing list boing@librelist.com. The archive of the mailing list can be checked out at http://librelist.com/browser/boing/. The other good way is to open an issue on github.

### ChangeLog

v0.3.1, Sep, 18 2012 - Fixed and upgraded the installation guide.

- Added attribute boing.config for storing global configuration variables.
- Added argument --no-gui for running Boing without a display server.
- .ui files are automatically compiled when the package is installed.
- boing.VERSION changed into boing.\_\_\_version\_\_\_
- The installation guide has been updated.
- Added documentation and unit test for module *boing.utils.url*.

v0.3.0, Sep, 10 2012 – First public release.

v0.2.0, Apr, 1 2012 - Architetecture wide modifications.

v0.1.0, Jan, 1 2012 - Pre-release.

### **Authors**

- Paolo Olivo (MSc, Milano Bicocca, 2009) is a contract engineer at INRIA Lille. His interests include software engineering and development for tactile and gestural interaction. The present focus of his work is on programming tools for supporting research in Human-Computer Interaction.
- Nicolas Roussel (PhD/Hab, Paris-Sud, 2000/2007) is a senior researcher at INRIA Lille. His research lies in the field of Human-Computer Interaction with current primary interests in the design, implementation and evaluation of simple yet powerful tactile and gestural interactions. Other interests include engineering of interactive systems, window systems, computer-mediated communication and groupware.

### License

```
Source: http://www.gnu.org/licenses/gpl-2.0.txt

GNU GENERAL PUBLIC LICENSE

Version 2, June 1991

Copyright (C) 1989, 1991 Free Software Foundation, Inc.,

51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA

Everyone is permitted to copy and distribute verbatim copies

of this license document, but changing it is not allowed.

Preamble

The licenses for most software are designed to take away your

freedom to share and change it. By contrast, the GNU General Public
```

License is intended to guarantee your freedom to share and change free

software--to make sure the software is free for all its users. This General Public License applies to most of the Free Software Foundation's software and to any other program whose authors commit to using it. (Some other Free Software Foundation software is covered by the GNU Lesser General Public License instead.) You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs; and that you know you can do these things.

To protect your rights, we need to make restrictions that forbid anyone to deny you these rights or to ask you to surrender the rights. These restrictions translate to certain responsibilities for you if you distribute copies of the software, or if you modify it.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.

Also, for each author's protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors' reputations.

Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone's free use or not licensed at all.

The precise terms and conditions for copying, distribution and modification follow.

GNU GENERAL PUBLIC LICENSE TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The "Program", below, refers to any such program or work, and a "work based on the Program" means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term "modification".) Each licensee is addressed as "you". Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.

1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:

a) You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.

b) You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.

c) If the modified program normally reads commands interactively when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program.

In addition, mere aggregation of another work not based on the Program

with the Program (or with a work based on the Program) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:

a) Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections1 and 2 above on a medium customarily used for software interchange; or,

b) Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution, a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,

c) Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.

4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it. 6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.

7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system, which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free

Software Foundation. If the Program does not specify a version number of this License, you may choose any version ever published by the Free Software Foundation.

10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

#### NO WARRANTY

11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

#### END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

<one line to give the program's name and a brief idea of what it does.>
Copyright (C) <year> <name of author>

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the

GNU General Public License for more details. You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA. Also add information on how to contact you by electronic and paper mail. If the program is interactive, make it output a short notice like this when it starts in an interactive mode: Gnomovision version 69, Copyright (C) year name of author Gnomovision comes with ABSOLUTELY NO WARRANTY; for details type `show w'. This is free software, and you are welcome to redistribute it under certain conditions; type `show c' for details. The hypothetical commands `show w' and `show c' should show the appropriate parts of the General Public License. Of course, the commands you use may be called something other than `show w' and `show c'; they could even be mouse-clicks or menu items--whatever suits your program. You should also get your employer (if you work as a programmer) or your school, if any, to sign a "copyright disclaimer" for the program, if necessary. Here is a sample; alter the names: Yoyodyne, Inc., hereby disclaims all copyright interest in the program `Gnomovision' (which makes passes at compilers) written by James Hacker.

<signature of Ty Coon>, 1 April 1989 Ty Coon, President of Vice

This General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Lesser General Public License instead of this License.

### **Todo list**

#### **Toolkit todo**

- Today or tomorrow:
- Improve docs and unit test for modules boing.utils.QPath and boing.utils.fileutils.
- Add docs and unit test for class boing.utils.url.URL on MS Windows.
- This week:
- · Write more tutorials.
- Upgrade module *boing.core* documentation.
- Someday:

Bugs and unittest:

• Add boing.test.nodes.test\_loader cases for the data processing nodes.

• Improve class QPath: regular expression compilation, join method, add unittest. The command:

raises an error if QPath.\_iterProp() returns a real iterator.

- when boing.create() raises an exception, it shows the lower URI and not the original one. This may be misleading for users.
- The player: 's playlist has some model trouble: when I drag and drop some files from a folder to the root level before the folder an Exception is raised. Sometimes files desappears.
- Handle when a source has been closed and when to start players (e.g. if TCP socked has been disconnected, TcpServer turned off).
- Resolve the UDP socket reuse port issue on Windows.

#### Pipeline architecture:

- The class Producer should also automatically know whether being active or not, like the class WiseWorker does. Check the 'tag' structure.
- The class Node shouldn't be a QObject?
- Improve Graphers (Graphers should draw themselves).
- · Add exclusive requests in order to optimize productivity.

#### Data model:

- json and pickle decoders should someway know what they produce.
- Check the quickdict constructor: if an hierarchical dictionary is passed to the constructor not all the hierarchy is transformed to a quickdict.

#### Functionalities:

- Encoder and Decoders in module boing.nodes.encoding should inherit boing.nodes.Encoder and boing.node.Decoder.
- Find a way so that the boing.node.loader can create nodes from external source files, so that users can add custom nodes.
- Develop the transformation node, which transforms the data hierarchy (JSON-schema validator).
- Develop evdev and uinput in&out bridges.
- Enable remote node.
- · Improve Contact Viz.
- Consider adding the module libfilter.filtering.signal to *boing.filtering*.
- Develop lib tIO cython bindings.
- When Qt4.8 will be available, add multicast support to UdpSocket.

#### Gesture Recognition:

- Prepare the directory with the gesture templates that the recognizer can use.
- Fix the recognition nodes.
- Support 1\$ algorithm.

Docs:

• Check which Ubuntu packages are really necessary.

#### Docs todo

#### Todo

Describe how to configure the pipeline dinamically

(The original entry is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/boing.rst, line 94.)

#### Todo

Comment module boing.filtering.

(The original entry is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/boing.filtering.rst line 29.)

#### Todo

Improve docs for the module boing.net.tcp

(The original entry is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/boing.net.tcp.rst, line 24.)

#### Todo

Improve docs for the module boing.net.udp

(The original entry is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/boing.net.udp.rst, line 24.)

#### Todo

Describe the data model.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/datamodel.rst, line 24.)

#### Todo

Describe an example of functional node.

(The original entry is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/developer.rst, line 57.)

#### Todo

Speak about the default nodes and the node uris convention. Also add a link to the Nodes reference table.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/functionalities.rst line 24.)

#### Todo

Describe data logging and replaying (both OSC and JSON formats).

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/functionalities.rst line 46.)

#### Todo

Describe the recorder tool.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/functionalities.rst line 52.)

#### Todo

Describe the Player tool.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/functionalities.rst line 65.)

#### Todo

Describe the calibration node.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/functionalities.rst line 81.)

#### Todo

Describe the filtering module.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/functionalities.rst line 87.)

#### Todo

Logging utils tutorial

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/logging.rst, line 24.)

#### Todo

multi-touch utilities tutorial.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/multitouch.rst, line 24.)

#### Todo

Improve the OSC tutorial.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/osc.rst, line 24.)

#### Todo

• Describe the composite nodes and node syntax (+ and | operators).

(The original entry is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/pipeline.rst, line 406.)

#### Todo

Data redirection tutorial

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/redirection.rst, line 24.)

#### Todo

Script advanced options tutorial

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/scriptadvanced.rs line 24.)

#### Todo

Improve the TUIO tutorial.

(The *original entry* is located in /home/docs/checkouts/readthedocs.org/user\_builds/boing/checkouts/stable/doc/source/tuio.rst, line 24.)

### **Indices and tables**

- genindex
- modindex
- search

# Python Module Index

# b

boing, 20 boing.core, 21 boing.filtering,22 boing.gesture,23 boing.gesture.rubine,23 boing.gesture.utils,23 boing.net,23 boing.net.bytes,23 boing.net.ip,26 boing.net.json,24 boing.net.ntp,27 boing.net.osc,25 boing.net.pickle,25 boing.net.slip,24 boing.net.tcp,26 boing.net.udp, 27 boing.nodes,27 boing.utils, 29boing.utils.url, 29

### Index

# Symbols

\_consume() (boing.core.boing.core.Consumer method), 22

# Α

addrToString() (in module boing.net.ip), 26 aggregateDemand() (boing.core.boing.core.Producer method), 22 assertIsInstance() (in module boing.utils), 29

# В

boing (module), 20 boing.activateConsole() (in module boing), 21 boing.core (module), 21 boing.core.Consumer (class in boing.core), 22 boing.core.Offer (class in boing.core), 21 boing.core.Producer (class in boing.core), 21 boing.core.QRequest (class in boing.core), 21 boing.core.Request (class in boing.core), 21 boing.create() (in module boing), 20 boing.filtering (module), 22 boing.gesture (module), 23 boing.gesture.rubine (module), 23 boing.gesture.utils (module), 23 boing.net (module), 23 boing.net.bytes (module), 23 boing.net.Decoder (class in boing.net), 23 boing.net.Encoder (class in boing.net), 23 boing.net.ip (module), 26 boing.net.json (module), 24 boing.net.ntp (module), 27 boing.net.osc (module), 25 boing.net.pickle (module), 25 boing.net.slip (module), 24 boing.net.tcp (module), 26 boing.net.udp (module), 27 boing.nodes (module), 27 boing.utils (module), 29 boing.utils.url (module), 29

boundingBox() (in module boing.gesture.utils), 23

### С

config (in module boing), 20 Console (class in boing.utils), 29

# D

datetime2ntp() (in module boing.net.ntp), 27 decode() (boing.net.bytes.Decoder method), 24 decode() (boing.net.json.Decoder method), 25 decode() (boing.net.osc.Decoder method), 25 decode() (boing.net.pickle.Decoder method), 26 decode() (boing.net.slip.Decoder method), 24 decode() (in module boing.net.bytes), 23 decode() (in module boing.net.json), 24 decode() (in module boing.net.pickle), 25 decode() (in module boing.net.slip), 24 Decoder (class in boing.net.bytes), 24 Decoder (class in boing.net.json), 25 Decoder (class in boing.net.osc), 25 Decoder (class in boing.net.pickle), 26 Decoder (class in boing.net.slip), 24 deepDump() (in module boing.utils), 29 demandChanged (boing.core.boing.core.Producer attribute), 22 demandedOffer() (boing.core.boing.core.Producer method), 22 demandedOfferChanged (boing.core.boing.core.Producer attribute), 22 DiffArgumentFunctor (class in boing.nodes), 28 Dump (class in boing.nodes), 27

# Ε

Editor (class in boing.nodes), 28 encode() (boing.net.bytes.Encoder method), 23 encode() (boing.net.json.Encoder method), 25 encode() (boing.net.osc.Encoder method), 25 encode() (boing.net.pickle.Encoder method), 26 encode() (boing.net.slip.Encoder method), 24

encode() (in module boing.net.bytes), 23 encode() (in module boing.net.json), 24 encode() (in module boing.net.pickle), 25 encode() (in module boing.net.slip), 24 Encoder (class in boing.net.bytes), 23 Encoder (class in boing.net.json), 24 Encoder (class in boing.net.osc), 25 Encoder (class in boing.net.pickle), 26 Encoder (class in boing.net.slip), 24

### F

fragment (boing.utils.url.URL attribute), 30

# G

get() (boing.nodes.Editor method), 28

# Н

host (boing.utils.url.URL\_site attribute), 31

# I

isAbsolute() (boing.utils.url.URL\_path method), 32 items() (boing.core.boing.core.Request method), 21 items() (boing.nodes.Editor method), 28

# K

kind (boing.utils.url.URL attribute), 29

### L

Lag (class in boing.nodes), 28

# Μ

meetsRequest() (boing.core.boing.core.Producer method), 22 mode() (boing.nodes.Dump method), 28

# Ν

ntp2datetime() (in module boing.net.ntp), 27 ntpDecode() (in module boing.net.ntp), 27 ntpEncode() (in module boing.net.ntp), 27 ntpFromServer() (in module boing.net.ntp), 27

# 0

offer() (boing.core.boing.core.Producer method), 22 offerChanged (boing.core.boing.core.Producer attribute), 22 opaque (boing.utils.url.URL attribute), 30

# Ρ

password (boing.utils.url.URL\_site attribute), 31 path (boing.utils.url.URL attribute), 30 port (boing.utils.url.URL\_site attribute), 31 postProduct() (boing.core.boing.core.Producer method), 22 push() (boing.utils.Console method), 29

# Q

query (boing.utils.url.URL attribute), 30

# R

request() (boing.core.boing.core.Consumer method), 22 reset() (boing.net.bytes.Decoder method), 24 reset() (boing.net.bytes.Encoder method), 23 reset() (boing.net.json.Decoder method), 25 reset() (boing.net.json.Encoder method), 25 reset() (boing.net.osc.Decoder method), 25 reset() (boing.net.osc.Encoder method), 25 reset() (boing.net.pickle.Decoder method), 26 reset() (boing.net.pickle.Encoder method), 26 reset() (boing.net.slip.Decoder method), 24 reset() (boing.net.slip.Encoder method), 24 reset() (boing.net.slip.Encoder method), 24

# S

scheme (boing.utils.url.URL attribute), 30 set() (boing.nodes.Editor method), 28 setMode() (boing.nodes.Dump method), 28 site (boing.utils.url.URL attribute), 30

### Т

test() (boing.core.boing.core.Request method), 21 Timekeeper (class in boing.nodes), 28

# U

updateBoundingBox() (in module boing.gesture.utils), 23 URL (class in boing.utils.url), 29 URL\_path (class in boing.utils.url), 31 URL\_query (class in boing.utils.url), 32 URL\_site (class in boing.utils.url), 31 user (boing.utils.url.URL site attribute), 31